# Cleveland Clinic Laboratories

# D-dimer to Rule Out Venous Thromboembolism

### **Background Information**

Venous thromboembolism is a serious medical problem that can escalate rapidly to a life-threatening situation in the form of pulmonary embolism. The annual incidence of pulmonary embolism in the United States is estimated at 100,000 to 300,000 cases.<sup>1</sup>

Symptoms of venous thromboembolism or deep vein thrombosis (DVT) include pain and swelling in the affected arm or leg and associated erythema, tenderness and warmth in the affected limb and calf pain on foot dorsiflexion. Symptoms typically are unilateral. Symptoms of pulmonary embolism include dyspnea, pleuritic chest pain, hemoptysis, low-grade fever, and tachycardia.

The D-dimer has proven most useful in patients suspected of having pulmonary embolism and who have a low pretest probability of disease. Use of the Wells Criteria has shown to be a reliable and reproducible means of determining this pretest probability. While DVT cannot be completely ruled out or confirmed with the Wells Criteria, it can help inform interpretation of subsequent diagnostic tests and reduce the need for invasive testing.

An estimated 70 percent of patients presenting in the emergency room with symptoms of DVT do not have the disorder.<sup>1</sup> Therefore, a means for rapidly and accurately differentiating between patients with DVT and those without is critical to defining subsequent appropriate therapy to prevent pulmonary embolism.

Several techniques have been proposed in the past decade for detecting small, deep thrombi, including CT venography, duplex scanning and MRI. These techniques, while effective, are time-consuming, expensive and, in the case of CT venography, expose patients to radiation.<sup>2</sup>

The D-dimer assay offers a rapid, non-invasive, relatively inexpensive *in vitro* method to rule out venous thromboembolism, DVT or pulmonary embolism. The assay provides a

quantitative measure of D-dimer. For suspected DVT, a D-dimer level below 500 ng/mL FEU has a Negative Predictive Value (NPV) of 99.2% and a sensitivy of 98.9 %. For suspected pulmunary embolism, a D-dimer below 500 ng/mL FEU has a NPV of 99.1% and a sensitivity of 97.8%.

The initial insult to the vein initiates the coagulation cascade. Fibrin produced during this process, together with platelet, forms the thrombus at the site of injury. During subsequent fibrinolysis, plasmin cleaves factor XIIIa–crosslinked fibrin into several intermediate forms, including D-dimer fragments. D-dimer fragments, resulting from terminal fibrin degradation, are composed of smaller segments of crosslinked fibrin and are produced only during fibrinolysis.

Under normal conditions, D-dimer is undetectable in the blood. Therefore, D-dimer is a marker for intravascular coagulation, and its presence in the blood is suggestive of thrombosis. To make a definitive diagnosis of venous thromboembolism, DVT or pulmonary embolism, patients with an elevated D-dimer should undergo additional testing such as ultrasonography, ventilation perfusion lung scan and chest computed tomography (CT).<sup>3</sup>

# **Clinical Indications**

Rule out venous thromboembolism, DVT or pulmonary embolism in the presence of risk factors and clinical symptoms.

### Interpretation

Negative: D-dimer < 500 ng/ml.

#### Limitations of the Assay

D-dimer should not be used as a stand-alone test.

Elevated D-dimer may be due to recent surgery, trauma, or infection. Elevated levels are also seen with liver disease, pregnancy, eclampsia, cardiovascular disease, and some cancers.



# **Cleveland Clinic Laboratories**

# References

- 1. Bockenstedt P. D-Dimer in Venous Thromboembolism. *N Engl J Med*. 2003;349:1203-1204.
- 2. Stein PD, Matta F. Acute pulmonary embolism. *Curr Probl Cardiol.* 2010 Jul;35(7):314-76.
- 3. Salaun PY, Couturaud F, LE Duc-Pennec A, Lacut K, LE Roux PY, Guillo P, Pennec PY, Cornily JC, Leroyer C, LE Gal G. Non-invasive diagnosis of pulmonary embolism. *Chest*. 2010;Aug.19, e-pub ahead of print.

# **Test Overview**

Test Name	D-dimer
Methodology	Turbidimetric Immunoassay (TUI)
Specimen Requirements	Volume/Size: 2 mL; Type: Plasma; Tube/Container: Sodium citrate (Lt. Blue); Transport Temperature: Frozen
Minimum Specimen Requirements	Volume/Size: 1 mL
Special Information	3.2% sodium citrate is the preferred anticoagulant recommended by CLSI.
Reference Range	< 500 ng/mL FEU
Clinical Information	Useful in the evaluation of DIC and fibrinolytic abnormalities. Useful in the evaluation of deep vein thrombosis. A negative result (< 500 ng/mL) may be helpful in the exclusion of venous thrombosis.
Billing Code	26156
CPT Code	85379

### **Technical Information Contact:**

Laila Vengal, MT(ASCP) 216.445.1862 vengall@ccf.org

#### **Scientific Information Contacts:**

Kandice Kottke-Marchant, MD, PhD 216.444.2484 marchak@ccf.org Joyce Heesun Rogers, MD, PhD 216.445.2719 Rogersj5@ccf.org